

**VDA**

„Delivery Instruction with EDI“

**4905**

**Version 4.0, April 1996**

**EDI Steering Committee (AK KIT)**

Publisher: Verband der Automobilindustrie  
Behrenstraße 35  
Postbox 8 04 62  
10004 Berlin  
Telephone 030/897842-221  
Telefax 030/897842-606  
Internet: [www.vda.de](http://www.vda.de)

Copyright  
Re-print and every other form  
of duplication are only permitted if  
the source is quoted.

**VDA**

Verband der  
Automobilindustrie

**Disclaimer of warranty**

The VDA Recommendations may be freely used by anyone. Users are responsible for correct application of the recommendations case by case.

The Recommendations take into account the state of the art prevailing at the time of the respective issue. Use of the VDA Recommendations does not absolve anyone of responsibility for his/her own actions. All users act at their own risk. VDA and those involved in the development of VDA Recommendations cannot accept any liability.

Anyone noticing inaccuracies in the application of the VDA Recommendations or the possibility of incorrect interpretation is requested to notify VDA of this promptly so that any defects/shortfalls can be eliminated.

**Attention:**

This document is NOT the complete documentation of VDA 4905. It is an excerpt of the original German document and is solely intended for explanation of the record structures.

**TOC**

**1 MESSAGE STRUCTURE.....4**

**2 BRANCHING DIAGRAM .....5**

**3 SEGMENTS .....6**


## Structure / Table of Contents

Counter	No	Tag	St	MaxOcc	Level	Content
0010	1	<b>511</b>	M	1	0	header record delivery instruction
0020		<b>SG1</b>	M	9999999	1	512-513-514-515-517-518
0030	2	<b>512</b>	M	1	1	unique delivery instruction data
0040	3	<b>513</b>	M	1	2	accrual and call off data
0050	4	<b>514</b>	K	9999999	2	additional call off data
0060	5	<b>515</b>	K	1	2	Ford US call off data (for LABs from USA, Canada, Mexico only)
0060	6	<b>517</b>	K	9999999	2	packaging data
0070	7	<b>518</b>	K	9999999	2	call off text
0080	8	<b>519</b>	M	1	0	trailer record delivery instruction

Counter = Counter of record/group within the standard  
 No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the record/group

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used

### Branching Diagram of Used Records/Groups



Tag
St MaxOcc
No
Counter

Tag = Record/Group Tag  
 St = Status (M=Mandatory, C or K=Conditional, R=Required, O=Optional, A=Advised, D=Dependent)  
 MaxOcc = Maximum occurrence of the record/group  
 No = Consecutive record number  
 Counter = Counter of record/group within the standard

## Record Types

Counter	No	Tag	St	MaxOcc	Level	Name
---------	----	-----	----	--------	-------	------

0010	1	<b>511</b>	M	1	0	header record delivery instruction
------	---	------------	---	---	---	------------------------------------

Standard				
Tag	St	P	F	Name
511_01	M	1	N3	record type
511_02	M	4	N2	version number
511_03	M	6	A9	customer number
511_04	M	15	A9	supplier number
511_05	M	24	N5	old (previous) transmission number
511_06	M	29	N5	new transmission number
511_07	M	34	N6	transmission date
511_08	K	40	N6	date of resetting the cumulative received quantity to zero
511_09	K	46	A83	blank

**Remark:**  
1 x per transmission

**Example:**

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the record/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C or K=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used

## Record Types

Counter	No	Tag	St	MaxOcc	Level	Name
	0020	<b>SG1</b>	M	9999999	1	<b>512-513-514-515-517-518</b>
	0030	<b>2 512</b>	M	1	1	<b>unique delivery instruction data</b>

Standard				
Tag	St	P	F	Name
512_01	M	1	N3	record type
512_02	M	4	N2	version number
512_03	M	6	A3	customer plant
512_04	M	9	N9	call off number new
512_05	M	18	N6	call off date new
512_06	M	24	N9	call off number old
512_07	M	33	N6	call off date old
512_08	M	39	A22	customer's article code
512_09	K	61	A22	supplier's article code
512_10	K	83	A12	order / contract number
512_11	M	95	A5	unloading point (point of discharge)
512_12	M	100	A4	customer reference
512_13	M	104	A2	quantity unit
512_14	M	106	A1	delivery interval
512_15	K	107	N1	production authorisation
512_16	K	108	N1	material authorisation
512_17	M	109	A1	usage key
512_18	K	110	A7	account
512_19	K	117	A7	storage
512_20	K	124	A5	blank

**Remark:**

Once per part number and plant

**Example:**

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the record/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C or K=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used

## Record Types

Counter	No	Tag	St	MaxOcc	Level	Name
0020		<b>SG1</b>	M	9999999	1	<b>512-513-514-515-517-518</b>
0040	3	<b>513</b>	M	1	2	<b>accrual and call off data</b>

Standard				
Tag	St	P	F	Name
513_01	M	1	N3	record type
513_02	M	4	N2	version number
513_03	M	6	N6	entry date last delivery
513_04	M	12	N8	delivery note number last delivery
513_05	M	20	N6	delivery note date last delivery
513_06	M	26	N12	quantity last delivery
513_07	M	38	N10	cumulative figure
513_08	M	48	N6	call off date 1
513_09	M	54	N9	call off quantity 1
513_10	K	63	N6	call off date 2
513_11	K	69	N9	call off quantity 2
513_12	K	78	N6	call off date 3
513_13	K	84	N9	call off quantity 3
513_14	K	93	N6	call off date 4
513_15	K	99	N9	call off quantity 4
513_16	K	108	N6	call off date 5
513_17	K	114	N9	call off quantity 5
513_18	K	123	A6	blank

**Remark:**

Once per part number and plant

**Example:**

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the record/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C or K=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



## Record Types

Counter	No	Tag	St	MaxOcc	Level	Name	
	0020	<b>SG1</b>	M	9999999	1	<b>512-513-514-515-517-518</b>	
	0050	<b>4</b>	<b>514</b>	K	9999999	2	<b>additional call off data</b>

Standard				
Tag	St	P	F	Name
514_01	M	1	N3	record type
514_02	M	4	N2	version number
514_03	M	6	N6	call off date 6
514_04	M	12	N9	call off quantity 6
514_05	K	21	N6	call off date 7
514_06	K	27	N9	call off quantity 7
514_07	K	36	N6	call off date 8
514_08	K	42	N9	call off quantity 8
514_09	K	51	N6	call off date 9
514_10	K	57	N9	call off quantity 9
514_11	K	66	N6	call off date 10
514_12	K	72	N9	call off quantity 10
514_13	K	81	N6	call off date 11
514_14	K	87	N9	call off quantity 11
514_15	K	96	N6	call off date 12
514_16	K	102	N9	call off quantity 12
514_17	K	111	N6	call off date 13
514_18	K	117	N9	call off quantity 13
514_19	K	126	A3	blank

**Remark:**

n times per part number and plant

**Example:**

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the record/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C or K=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used

## Record Types

Counter	No	Tag	St	MaxOcc	Level	Name
0020		<b>SG1</b>	M	9999999	1	<b>512-513-514-515-517-518</b>
0060	5	<b>515</b>	K	1	2	<b>Ford US call off data (for LABs from USA, Canada, Mexico only)</b>

Standard				
Tag	St	P	F	Name
515_01	M	1	N3	record type
515_02	M	4	N2	version number
515_03	M	6	N6	production authorisation, start date
515_04	M	12	N6	production authorisation, end date
515_05	M	18	N10	production authorisation, cumulative quantity
515_06	M	28	N6	material authorisation, start date
515_07	M	34	N6	material authorisation, end date
515_08	M	40	N10	material authorisation, cumulative demand
515_09	K	50	A22	FPSD article code
515_10	K	72	A9	sub supplier
515_11	M	81	N6	planning horizon date
515_12	K	87	A14	point of use
515_13	K	101	N10	cumulative received quantity before resetting it to zero
515_14	K	111	A18	blank

**Remark:**

Once per part number and plant

**Example:**

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the record/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C or K=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used

## Record Types

Counter	No	Tag	St	MaxOcc	Level	Name
	0020	<b>SG1</b>	M	9999999	1	<b>512-513-514-515-517-518</b>
	0060	<b>517</b>	K	9999999	2	<b>packaging data</b>

Standard				
Tag	St	P	F	Name
517_01	M	1	N3	record type
517_02	M	4	N2	version number
517_03	M	6	A22	customer's article code for the package
517_04	K	28	A22	supplier's article number for the package
517_05	M	50	N7	package capacity
517_06	K	57	A72	blank

**Remark:**

n times per part number and plant

**Example:**

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the record/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C or K=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used

## Record Types

Counter	No	Tag	St	MaxOcc	Level	Name
0020		<b>SG1</b>	M	9999999	1	<b>512-513-514-515-517-518</b>
0070	7	<b>518</b>	K	9999999	2	<b>call off text</b>

Standard				
Tag	St	P	F	Name
518_01	M	1	N3	record type
518_02	M	4	N2	version number
518_03	M	6	A40	call off text 1
518_04	K	46	A40	call off text 2
518_05	K	86	A40	call off text 3
518_06	K	126	A3	blank

**Remark:**

n times per part number and plant

**Example:**

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the record/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C or K=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used

## Record Types

Counter	No	Tag	St	MaxOcc	Level	Name
---------	----	-----	----	--------	-------	------

0080	8	<b>519</b>	M	1	0	trailer record delivery instruction
------	---	------------	---	---	---	-------------------------------------

Standard				
Tag	St	P	F	Name
519_01	M	1	N3	record type
519_02	M	4	N2	version number
519_03	M	6	N7	counter record 511
519_04	M	13	N7	counter record 512
519_05	M	20	N7	counter record 513
519_06	M	27	N7	counter record 514
519_07	M	34	N7	counter record 517
519_08	M	41	N7	counter record 518
519_09	M	48	N7	counter record 519
519_10	M	55	N7	counter record 515
519_11	K	62	A67	blank

**Remark:**

Once per transmission

**Example:**

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the record/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C or K=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used

**Record Types**

**511\_02**      version number

<b>Code</b>	<b>Name/Description</b>
-------------	-------------------------

<b>02</b>	Version 02
-----------	------------

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

**Record Types****512\_02**      version number**Code**      **Name/Description****01**      Version 01

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

## Record Types

**512\_13**      quantity unit

Code	Name/Description
<b>KG</b>	kilogram
<b>KM</b>	kilometre
<b>L</b>	litre
<b>M</b>	metre
<b>M2</b>	square metre
<b>M3</b>	cubic metre
<b>ST</b>	piece
<b>T</b>	ton

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used



## Record Types

**512\_14** delivery interval

Code	Name/Description
------	------------------

L	according to transmitted call-off date
---	--

M	monthly
---	---------

T	daily
---	-------

W	weekly
---	--------

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

## Record Types

**512\_17** usage key

Code	Name/Description
<b>E</b>	sparepart (general)
<b>M</b>	sample (initial)
<b>P</b>	pilot
<b>S</b>	series
<b>U</b>	series and sparepart
<b>V</b>	test
<b>X</b>	other
<b>Y</b>	sample
<b>Z</b>	additional demand

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

**Record Types**

**513\_02**      version number

<b>Code</b>	<b>Name/Description</b>
-------------	-------------------------

<b>01</b>	Version 01
-----------	------------

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

## Record Types

**513\_08** call off date 1

Code	Name/Description
<b>000000</b>	end of delivery instruction Used to indicate the last field in a delivery instruction for a specific part or article number. The related quantity field and all subsequent fields of the record are filled with BLANK (space).
<b>222222</b>	no demand Used to indicate that there is no demand for this part / article number. The related quantity fields and all other following fields in the record are filled with BLANK (space).
<b>333333</b>	backorder quantity Used to indicate the backorder quantity.
<b>444444</b>	immediate demand Used to indicate immediate demand
<b>555555</b>	transition to weekly or monthly demand figures Used to indicate that the following demand figures are weekly or monthly figures. The related quantity field must be filled with zeros. If all figures in the delivery instruction are weekly or monthly values then the first date of the schedule shall contain the value 555555.
<b>999999</b>	remaining demand Used to indicate that the quantity field contains the remaining demand of perhaps several months without more detailed time specification.

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

## Record Types

**513\_10** call off date 2

Code	Name/Description
<b>000000</b>	end of delivery instruction Used to indicate the last field in a delivery instruction for a specific part or article number. The related quantity field and all subsequent fields of the record are filled with BLANK (space).
<b>222222</b>	no demand Used to indicate that there is no demand for this part / article number. The related quantity fields and all other following fields in the record are filled with BLANK (space).
<b>333333</b>	backorder quantity Used to indicate the backorder quantity.
<b>444444</b>	immediate demand Used to indicate immediate demand
<b>555555</b>	transition to weekly or monthly demand figures Used to indicate that the following demand figures are weekly or monthly figures. The related quantity field must be filled with zeros. If all figures in the delivery instruction are weekly or monthly values then the first date of the schedule shall contain the value 555555.
<b>999999</b>	remaining demand Used to indicate that the quantity field contains the remaining demand of perhaps several months without more detailed time specification.

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

## Record Types

**513\_12** call off date 3

Code	Name/Description
<b>000000</b>	end of delivery instruction Used to indicate the last field in a delivery instruction for a specific part or article number. The related quantity field and all subsequent fields of the record are filled with BLANK (space).
<b>222222</b>	no demand Used to indicate that there is no demand for this part / article number. The related quantity fields and all other following fields in the record are filled with BLANK (space).
<b>333333</b>	backorder quantity Used to indicate the backorder quantity.
<b>444444</b>	immediate demand Used to indicate immediate demand
<b>555555</b>	transition to weekly or monthly demand figures Used to indicate that the following demand figures are weekly or monthly figures. The related quantity field must be filled with zeros. If all figures in the delivery instruction are weekly or monthly values then the first date of the schedule shall contain the value 555555.
<b>999999</b>	remaining demand Used to indicate that the quantity field contains the remaining demand of perhaps several months without more detailed time specification.

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

## Record Types

**513\_14** call off date 4

Code	Name/Description
<b>000000</b>	end of delivery instruction Used to indicate the last field in a delivery instruction for a specific part or article number. The related quantity field and all subsequent fields of the record are filled with BLANK (space).
<b>222222</b>	no demand Used to indicate that there is no demand for this part / article number. The related quantity fields and all other following fields in the record are filled with BLANK (space).
<b>333333</b>	backorder quantity Used to indicate the backorder quantity.
<b>444444</b>	immediate demand Used to indicate immediate demand
<b>555555</b>	transition to weekly or monthly demand figures Used to indicate that the following demand figures are weekly or monthly figures. The related quantity field must be filled with zeros. If all figures in the delivery instruction are weekly or monthly values then the first date of the schedule shall contain the value 555555.
<b>999999</b>	remaining demand Used to indicate that the quantity field contains the remaining demand of perhaps several months without more detailed time specification.

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

## Record Types

**513\_16** call off date 5

Code	Name/Description
<b>000000</b>	end of delivery instruction Used to indicate the last field in a delivery instruction for a specific part or article number. The related quantity field and all subsequent fields of the record are filled with BLANK (space).
<b>222222</b>	no demand Used to indicate that there is no demand for this part / article number. The related quantity fields and all other following fields in the record are filled with BLANK (space).
<b>333333</b>	backorder quantity Used to indicate the backorder quantity.
<b>444444</b>	immediate demand Used to indicate immediate demand
<b>555555</b>	transition to weekly or monthly demand figures Used to indicate that the following demand figures are weekly or monthly figures. The related quantity field must be filled with zeros. If all figures in the delivery instruction are weekly or monthly values then the first date of the schedule shall contain the value 555555.
<b>999999</b>	remaining demand Used to indicate that the quantity field contains the remaining demand of perhaps several months without more detailed time specification.

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used



**Record Types**

**514\_02**      version number

<b>Code</b>	<b>Name/Description</b>
-------------	-------------------------

<b>01</b>	Version 01
-----------	------------

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

## Record Types

**514\_03** call off date 6

Code	Name/Description
<b>000000</b>	end of delivery instruction Used to indicate the last field in a delivery instruction for a specific part or article number. The related quantity field and all subsequent fields of the record are filled with BLANK (space).
<b>222222</b>	no demand Used to indicate that there is no demand for this part / article number. The related quantity fields and all other following fields in the record are filled with BLANK (space).
<b>333333</b>	backorder quantity Used to indicate the backorder quantity.
<b>444444</b>	immediate demand Used to indicate immediate demand
<b>555555</b>	transition to weekly or monthly demand figures Used to indicate that the following demand figures are weekly or monthly figures. The related quantity field must be filled with zeros. If all figures in the delivery instruction are weekly or monthly values then the first date of the schedule shall contain the value 555555.
<b>999999</b>	remaining demand Used to indicate that the quantity field contains the remaining demand of perhaps several months without more detailed time specification.

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

## Record Types

**514\_05** call off date 7

Code	Name/Description
<b>000000</b>	end of delivery instruction Used to indicate the last field in a delivery instruction for a specific part or article number. The related quantity field and all subsequent fields of the record are filled with BLANK (space).
<b>222222</b>	no demand Used to indicate that there is no demand for this part / article number. The related quantity fields and all other following fields in the record are filled with BLANK (space).
<b>333333</b>	backorder quantity Used to indicate the backorder quantity.
<b>444444</b>	immediate demand Used to indicate immediate demand
<b>555555</b>	transition to weekly or monthly demand figures Used to indicate that the following demand figures are weekly or monthly figures. The related quantity field must be filled with zeros. If all figures in the delivery instruction are weekly or monthly values then the first date of the schedule shall contain the value 555555.
<b>999999</b>	remaining demand Used to indicate that the quantity field contains the remaining demand of perhaps several months without more detailed time specification.

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

## Record Types

**514\_07** call off date 8

Code	Name/Description
<b>000000</b>	end of delivery instruction Used to indicate the last field in a delivery instruction for a specific part or article number. The related quantity field and all subsequent fields of the record are filled with BLANK (space).
<b>222222</b>	no demand Used to indicate that there is no demand for this part / article number. The related quantity fields and all other following fields in the record are filled with BLANK (space).
<b>333333</b>	backorder quantity Used to indicate the backorder quantity.
<b>444444</b>	immediate demand Used to indicate immediate demand
<b>555555</b>	transition to weekly or monthly demand figures Used to indicate that the following demand figures are weekly or monthly figures. The related quantity field must be filled with zeros. If all figures in the delivery instruction are weekly or monthly values then the first date of the schedule shall contain the value 555555.
<b>999999</b>	remaining demand Used to indicate that the quantity field contains the remaining demand of perhaps several months without more detailed time specification.

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

## Record Types

**514\_09** call off date 9

Code	Name/Description
<b>000000</b>	end of delivery instruction Used to indicate the last field in a delivery instruction for a specific part or article number. The related quantity field and all subsequent fields of the record are filled with BLANK (space).
<b>222222</b>	no demand Used to indicate that there is no demand for this part / article number. The related quantity fields and all other following fields in the record are filled with BLANK (space).
<b>333333</b>	backorder quantity Used to indicate the backorder quantity.
<b>444444</b>	immediate demand Used to indicate immediate demand
<b>555555</b>	transition to weekly or monthly demand figures Used to indicate that the following demand figures are weekly or monthly figures. The related quantity field must be filled with zeros. If all figures in the delivery instruction are weekly or monthly values then the first date of the schedule shall contain the value 555555.
<b>999999</b>	remaining demand Used to indicate that the quantity field contains the remaining demand of perhaps several months without more detailed time specification.

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

## Record Types

**514\_11** call off date 10

Code	Name/Description
<b>000000</b>	end of delivery instruction Used to indicate the last field in a delivery instruction for a specific part or article number. The related quantity field and all subsequent fields of the record are filled with BLANK (space).
<b>222222</b>	no demand Used to indicate that there is no demand for this part / article number. The related quantity fields and all other following fields in the record are filled with BLANK (space).
<b>333333</b>	backorder quantity Used to indicate the backorder quantity.
<b>444444</b>	immediate demand Used to indicate immediate demand
<b>555555</b>	transition to weekly or monthly demand figures Used to indicate that the following demand figures are weekly or monthly figures. The related quantity field must be filled with zeros. If all figures in the delivery instruction are weekly or monthly values then the first date of the schedule shall contain the value 555555.
<b>999999</b>	remaining demand Used to indicate that the quantity field contains the remaining demand of perhaps several months without more detailed time specification.

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

## Record Types

**514\_13** call off date 11

Code	Name/Description
<b>000000</b>	end of delivery instruction Used to indicate the last field in a delivery instruction for a specific part or article number. The related quantity field and all subsequent fields of the record are filled with BLANK (space).
<b>222222</b>	no demand Used to indicate that there is no demand for this part / article number. The related quantity fields and all other following fields in the record are filled with BLANK (space).
<b>333333</b>	backorder quantity Used to indicate the backorder quantity.
<b>444444</b>	immediate demand Used to indicate immediate demand
<b>555555</b>	transition to weekly or monthly demand figures Used to indicate that the following demand figures are weekly or monthly figures. The related quantity field must be filled with zeros. If all figures in the delivery instruction are weekly or monthly values then the first date of the schedule shall contain the value 555555.
<b>999999</b>	remaining demand Used to indicate that the quantity field contains the remaining demand of perhaps several months without more detailed time specification.

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

## Record Types

**514\_15** call off date 12

Code	Name/Description
<b>000000</b>	end of delivery instruction Used to indicate the last field in a delivery instruction for a specific part or article number. The related quantity field and all subsequent fields of the record are filled with BLANK (space).
<b>222222</b>	no demand Used to indicate that there is no demand for this part / article number. The related quantity fields and all other following fields in the record are filled with BLANK (space).
<b>333333</b>	backorder quantity Used to indicate the backorder quantity.
<b>444444</b>	immediate demand Used to indicate immediate demand
<b>555555</b>	transition to weekly or monthly demand figures Used to indicate that the following demand figures are weekly or monthly figures. The related quantity field must be filled with zeros. If all figures in the delivery instruction are weekly or monthly values then the first date of the schedule shall contain the value 555555.
<b>999999</b>	remaining demand Used to indicate that the quantity field contains the remaining demand of perhaps several months without more detailed time specification.

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used



## Record Types

**514\_17** call off date 13

Code	Name/Description
<b>000000</b>	end of delivery instruction Used to indicate the last field in a delivery instruction for a specific part or article number. The related quantity field and all subsequent fields of the record are filled with BLANK (space).
<b>222222</b>	no demand Used to indicate that there is no demand for this part / article number. The related quantity fields and all other following fields in the record are filled with BLANK (space).
<b>333333</b>	backorder quantity Used to indicate the backorder quantity.
<b>444444</b>	immediate demand Used to indicate immediate demand
<b>555555</b>	transition to weekly or monthly demand figures Used to indicate that the following demand figures are weekly or monthly figures. The related quantity field must be filled with zeros. If all figures in the delivery instruction are weekly or monthly values then the first date of the schedule shall contain the value 555555.
<b>999999</b>	remaining demand Used to indicate that the quantity field contains the remaining demand of perhaps several months without more detailed time specification.

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

**Record Types**

**515\_02**      version number

<b>Code</b>	<b>Name/Description</b>
-------------	-------------------------

<b>02</b>	Version 02
-----------	------------

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

**Record Types****517\_02**      version number**Code**            **Name/Description****01**              Version 01

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

**Record Types****518\_02** version number**Code** **Name/Description****01** Version 01

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used

**Record Types****519\_02**      version number**Code**            **Name/Description****03**                Version 03

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the record/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C or K=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used